

Sprint Software 1.06.00 Release Notes



Contents

Contents.....	2
1.06.00	3
Hardware Requirements	3
New Features.....	3
Summary	3
SPRS-34371 Enable seamless install on windows 10	3
SPRS-34378 Support the new v30 edition of the deskey security keys.....	4
Bug Fixes	4
Contact Information.....	5

1.06.00

Hardware Requirements

Item	Minimum Specification	Recommended Specification
CPU	i5 2.8GHz	i7 2.8GHz
Memory	8 GB RAM	8 GB RAM
Harddisk	240 GB SSD or hard disk	500 GB SSD
Graphics	32-bit colour, Direct-X V10 or later	32-bit colour, Direct-X V10 or later
Monitor Resolution	1280 x 1024	1920 x 1080
USB	4 USB Ports	4 USB Ports
Operating System	Windows 10 Professional x64	Windows 10 Professional x64

New Features

From 1.06.00 onwards Sprint Software is not supported on windows 7. For more information on windows 7 please contact customer support, using the details at the end of these release notes.

The focus of this release is to support installs on windows 10 Pro and lay the groundwork for future releases supporting windows 11 Pro.

Summary

Functional Area	Ref	Description
Installer	SPRS-34371	Remove dependency on Microsoft .NET framework 3.5 to allow seamless install on Windows 10. Update all libraries used in software to latest versions
Installer	SPRS-34378	Support the new v30 edition of the deskey security keys

SPRS-34371 Enable seamless install on windows 10

Previously parts of Sprint Software used Microsoft .NET 3.5 Framework. This is no longer supported by Microsoft and has to be installed manually on windows 10 systems (rather than included by default). This can cause operational difficulties for offshore installs/upgrades. We can also no longer provide an offline installer for .NET 3.5.

We have removed or upgraded all unsupported libraries. Sprint Software now runs on the fully supported Microsoft .NET 4.8 framework.

SPRS-34378 Support the new v30 edition of the deskey security keys
Sprint software now supports both the older security key and the new smaller keys:

Old key



New key



Bug Fixes

No Bug fixes were made to this release.

Contact Information

For further support please contact:

24/7 Emergency Helpline

T. +44 (0) 1252 877600

Email Support

support@sonardyne.com

Website

www.sonardyne.com